


Using Windows Movie Maker



About the menu bar and toolbar

You can use the commands in the menu bar to perform tasks in Windows Movie Maker. The procedures for completing tasks are described throughout Help by using the menu commands.

The toolbar provides an alternative to selecting commands on the menus. You can use the toolbar to perform common tasks quickly.

To show or hide the toolbar, on the **View** menu, click **Toolbar**. A check mark appears next to the **Toolbar** command on the menu when the toolbar is displayed.


About the storyboard

The storyboard is the default view in Windows Movie Maker. You can use the storyboard to look at the sequence or ordering of the clips in your project and easily rearrange them, if necessary. This view also lets you see any video effects or video transitions that have been added. You can also preview all of the clips in your current project. Audio clips that you have added to a project are not displayed on the storyboard; however, they are displayed in the timeline.

About the timeline

You can use the timeline to review or modify the timing of clips in your project. Use the timeline buttons to perform tasks such as changing the view of your project, zooming in or out on details of your project, recording narration, or adjusting the audio levels. The time is displayed as hours:minutes:seconds.hundredths of a second (h:mm:ss.hs). To trim unwanted portions of your clip, use the trim handles, which appear when you select a clip. You can also preview all of the clips in your current project which are displayed on the timeline.

The following illustration shows the timeline. All the clips in the timeline define your project. The timeline displays the following tracks to indicate what types of files you have added to your current project.



Video

The Video track lets you see what video clips, pictures, or titles you have added to the project. You can expand the Video track to show the corresponding audio accompanying the video, as well as any video transitions you have added. After a clip is added to the timeline, the name of the source file appears on that clip. If you add any video effects to the picture, video, or title, a small icon appears on the clips to indicate that a video effect has been added to that clip.

Transition

The Transition track lets you see any video transitions you have added to the timeline. This track only appears if you have expanded the Video track. Any video transitions you add from the Video Transitions folder appear on this track. When a transition is added to the timeline, the name of the transition is shown in the timeline. You can drag the start trim handle that appears when the transition is selected to increase or decrease its duration.

Audio

The Audio track lets you see the audio that is included in any video clips you have added to the project. Like the Transition track, you can only see the Audio track if you have expanded the Video track. If you select the audio clip on this track and delete it, the video portion is also removed from the Video track.


Audio/Music

The Audio/Music track lets you see any audio clips that you have added to the project. The name of the audio clip appears on the clip.


You can also add video clips to this track if you want the audio, but not the video, to play in your project and final movie.

Title Overlay


The Title Overlay track lets you see any titles or credits that you have added to the timeline. You can add multiple titles to this track at different points in your movie. The titles overlay the video that is displayed. You can drag the start or end trim handle that appears when the title is selected to increase or decrease its duration.



- To locate clips:
- Click on My Computer
 - Double click on your H: drive
 - Choose picture, video, or sound clip and click "Open"




Creating a storyboard



Click and drag pictures or video clip down to the open storyboard boxes to begin making your movie. You can drag one picture at a time or select them all and drag them all down at once.


Adding Video Effects



Click on the “View Video Effects” link on the left side of the screen or choose “Video Effects” in the drop down box on the top of the screen.


Click and drag the desired video effect to the “star” in the bottom corner of the storyboard element you want to add it to.

Adding Video Transitions



Click on the “View Video Transitions” link on the left side of the screen or choose “Video Transitions” in the drop down box on the top of the screen.


Click and drag the desired transition to the small box in between each storyboard element.



Click on the “Make Title or Credits” link on the left side of the screen.

Follow the steps to create your titles and credits.

Adding Music File



Make sure timeline is showing, then click and drag audio clip to the timeline.

You can click and drag audio clip to go anywhere in your storyboard or resize it to fit the desired length.